

# TOF Command-line Tool: User Manual

Aly Aly

February 1, 2023

## 1 Purpose of Tool

The purpose of this tool is to process direct event data files produced during IMAP-Lo calibrations. This tool is intended for use by any test operator or designated analysis team to create TOF histograms in 1D and 2D. For those reasons the only required input is a filepath to a DE\_RAW file produced by IMAP-Lo GSEOS in .csv format.

## 2 Quick Start

### 2.1 Installation

To install this tool download the tool folder where you want it. Make sure you have all the following packages installed: none, for now. Then you are ready to use the tool.

### 2.2 Fastest way to plot...

#### 2.2.1 Everything

Type the following in your favorite powershell/terminal from inside that directory.

```
python /path/to/tool/command_line_tool.py -f /path/to/file/XXX_RAW_DE_#####.csv
```

Replace `/path/to/file/` and `/path/to/tool/` with the paths on your machine. This command alone will produce plots in 2D of the data in the `.csv` file provided. The data will not be cleaned in anyway, i.e. all singles and doubles are plotted as well. The files will be saved in the same directory as the input file. Unless we specify the output file path, including the name, with the `-o` option, all plots are saved in the same directory as the input file. As an example if the `.csv` file is in a directory called `test_data`, the plots and a new `.csv` will be saved there as well. To find out more about `-o` see Section 2.3.

### 2.2.2 Triples and Golden triples (`-v` and `-ch`)

To make the same plots for triples then type the following code.

```
python command_line_tool.py -f XXX_RAW_DE_#####.csv -v 1 1 1 1
```

for golden triples:

```
python command_line_tool.py -f XXX_RAW_DE_#####.csv -v 1 1 1 1 -ch
```

, where the checksum filter is a conditional.

```
if abloute_value_of_checksum > 1 , then discard_event
```

To change the value of the checksum filter to 0.5 instead of 1, use the following code.

```
python command_line_tool.py -f XXX_RAW_DE_#####.csv -v 1 1 1 1 -ch 0.5
```

## 2.3 Output location and naming (`-o` and `-st`).

To put all output in a directory other than the input file the use the `-o` flag

```
python command_line_tool.py -f \path\to\csv\csv_filename.csv -o .\path\to\out\fil
```

This code will create all the output from Section 2.2.1 for file /path/to/csv/csv\_filename.csv in directory /path/to/csv/ and all files will have "filenames\_prefix" as the first part of the name. default is to use the input filename without the .csv. Some times the plot names are too long to use as figure titles so we can use the -st option to give the figures a title since default is "filenames\_prefix".

```
python command_line_tool.py -f \path\to\csv\csv_filename.csv -o .\path\to\out\fil
```

### 3 .csv file format

This tool ingests contents of a file produces by IMAP-Lo GSEOS. The files ingested have the string "DE\_RAW" in the file name. These files consist of rows that include the DE block with 500 counts maximum per block or row (see figure .

Figure 1: Example of a .csv file with DE\_RAW in file name

	A	B	C	D	E	F	G	H	I	J	K	L
1	SPIN_SECONDS	SPIN_SUBSECONDS	DIRECT_EVENT_COUNT	OFFSET_MS_000	VALIDSTART3_000	VALIDSTOP3_000	VALIDTOF3_000	TOF3_000	VALIDSTA	VALIDSTO	VALIDTOF	TOF2_000
2	412051771	40085	38	17238	1	1	1	1.86579497	0	0	0	0.31441
3	412051786	40077	138	18404	1	1	1	1.86579497	0	0	0	0.31441
4	412051786	40077	121	4134	1	1	1	4.53944006	0	0	0	0.31441
5	412051786	40077	144	5166	1	1	1	1.98410655	0	0	0	0.31441
6	412051786	40077	123	6156	1	1	1	4.878712636	0	0	0	0.31441
7	412051786	40077	144	7199	1	1	1	4.878712636	0	1	0	0.31441
8	412051786	40077	118	8193	1	1	1	4.711328321	0	0	0	0.31441
9	412051786	40077	129	9139	1	1	1	1.86579497	0	0	0	0.31441
10	412051786	40077	129	10319	1	1	1	1.86579497	0	0	0	0.31441

Number of events in block 000-499

valid strt3, stp3, tof3 flags for event 000

tof3 value for event 000

tof2 value for event 000